



USB CopyNotify! (Ver. 2.1)

Control & Monitor USB Device Usage
REMOTE DEPLOYMENT WIZARD

Index

1. Introduction.....	2
2. Installation.....	3
3. User Instructions.....	4
USB CopyNotify! Server IP Address.....	5
Add Machine Details.	6
Remove Machine Details	7
Select ALL.....	8
De Select ALL.....	9
Install USB CopyNotify!.....	10
Un Install USB CopyNotify!.....	11
Install Status Check.....	12
Save.....	13
Exit.....	14



USB CopyNotify! (Ver. 2.1)

Control & Monitor USB Device Usage
REMOTE DEPLOYMENT WIZARD

Introduction

USB CopyNotify! consists of 2 components, the USB CopyNotify! Server & the USB CopyNotify! Client.

The clients have to be loaded on all the machines that need to be monitored while the server is to be loaded on the machine on which you will be receive all the alerts and control the software.

If there are a large number of machines that need to have the client loaded, then it is more convenient to use the Remote Deployment Wizard. The remote deployment wizard has been created so as to help the user to remotely install USB CopyNotify! clients from a central location without having to physically go to each machine to complete the install.

The remote deployment wizard can be downloaded from

<http://www.usbcopynotify.com/downloads/RemoteDeploy.zip>

OR

The remote deployment wizard is available on the **Evaluation CD**. There is a file called RemoteDeploy.zip in the root/main directory of the **Evaluation CD**.

Once installed this Remote Deployment Wizard allows you

- to install USB CopyNotify! clients remotely.
- to un install USB CopyNotify! clients remotely.
- to check whether USB CopyNotify! client is running on a remote machine.

Notes :

- This wizard will only work on USB CopyNotify!, Ver. 1.4 and above
- You will need to install the .NET Framework 2.0 which can be freely downloaded from the Microsoft site.
- The currently logged in user on the machine on which the Remote Deployment Wizard has been setup has to have full access on the remote machines on which the clients will be installed.
- Remote Access & Remote Execution needs to be enabled on all the remote machines on which the clients will be installed.



USB CopyNotify! (Ver. 2.1)

Control & Monitor USB Device Usage
REMOTE DEPLOYMENT WIZARD

Installation

Once you have downloaded the remotedeploy.zip file, unzip the contents of the downloaded file into a newly created directory.

Copy the USBCopyNotify! Install (USBCopyNotify!.exe) into the above created directory.

Double Click on USBApplication.exe to start the Remote Deployment Wizard.




USB CopyNotify! (Ver. 2.1)

Control & Monitor USB Device Usage
REMOTE DEPLOYMENT WIZARD

User Instructions

The deployment wizard User Interface is broken up into 2 main areas i.e. a display area on the Left Hand Side. This display area will be filled by the IP addresses/Machine Names of the computers as specified by the user on which USB CopyNotify! client is to be installed.

The Right Hand Side has all the controls that will operate on the list of IP addresses/Machine Names that have been entered.






USB CopyNotify! (Ver. 2.1)

Control & Monitor USB Device Usage
REMOTE DEPLOYMENT WIZARD

USB CopyNotify! Server IP Address

This is where the user will enter the IP Address of the machine on which USB CopyNotify! Server is installed. This is required while doing the remote installation of the clients so as to specify the location of USB CopyNotify! Server.






USB CopyNotify! (Ver. 2.1)

Control & Monitor USB Device Usage
REMOTE DEPLOYMENT WIZARD

Add Machines Details:

This allows you to add to the list of IP addresses/Machine Names of the computers on which you wish to install USB CopyNotify! Client. Clicking on it will open a small data entry dialog where you can enter the IP address.

When you click on ADD the IP address will be added to the list of IP addresses.






USB CopyNotify! (Ver. 2.1)

Control & Monitor USB Device Usage
REMOTE DEPLOYMENT WIZARD

Remove Machine Details:

This allows you to remove the IP address / Machine Name from the list.

In order to select the IP address / Machine Name to be removed you will need to click on the check box next to the IP address / Machine Name in the list and then click on Remove Machine Details.





USB CopyNotify! (Ver. 2.1)


Control & Monitor USB Device Usage
REMOTE DEPLOYMENT WIZARD

Select ALL:

This will select all the IP addresses / Machine Names in the list.

Note :

All operations are executed only on the IP addresses / Machine Names that are selected.





USB CopyNotify! (Ver. 2.1)


Control & Monitor USB Device Usage
REMOTE DEPLOYMENT WIZARD

De Select ALL:

This will de select all the IP addresses / Machine Names in the list.

Note :

All operations are executed only on the IP addresses / Machine Names that are selected.





USB CopyNotify! (Ver. 2.1)

Control & Monitor USB Device Usage
REMOTE DEPLOYMENT WIZARD

Install USB CopyNotify!:


This will install USB CopyNotify! remotely on the selected IP address / Machine Name

In order to select the IP address / Machine Name you will need to click on the check box next to the IP address / Machine Name in the list.

Note :

The Install USB CopyNotify! Operation will be executed only on the IP addresses / Machine Names that are selected.

You will need to specify the USB CopyNotify! Server IP Address which will be applied to all the USB CopyNotify! Clients which are being remotely installed.





USB CopyNotify! (Ver. 2.1)

Control & Monitor USB Device Usage
REMOTE DEPLOYMENT WIZARD


Un Install USB CopyNotify!:

This will un install USB CopyNotify! remotely from the selected IP address / Machine Name.

In order to select the IP address / Machine Name you will need to click on the check box next to the IP address in the list.

Note :

The Un - Install USB CopyNotify! Operation will be executed only on the IP addresses / Machine Names that are selected.






USB CopyNotify! (Ver. 2.1)

Control & Monitor USB Device Usage
REMOTE DEPLOYMENT WIZARD

Install Status Check:

This will allow you to check whether USB CopyNotify! is running on the selected IP addresses / Machine Names. In order to select the IP address / Machine Name you will need to click on the check box next to the IP address / Machine Name in the list.





USB CopyNotify! (Ver. 2.1)

Control & Monitor USB Device Usage
REMOTE DEPLOYMENT WIZARD

Save:

This will allow you to save the List of IP addresses / Machine Names that have been entered as well as the last status.

The screenshot shows the 'USB CopyNotify! Remote Deployment' wizard window. It features a table with columns for 'IPAddress' and 'Status'. The table contains four rows: 192.168.1.161 (Running), 192.168.1.162 (Not Selected for Processing), 192.168.1.163 (Not Selected for Processing), and ws131 (Running). The 'Save' button in the right-hand panel is highlighted with a red box.

	IPAddress	Status
<input type="checkbox"/>	192.168.1.161	Running
<input checked="" type="checkbox"/>	192.168.1.162	Not Selected for Processing.
<input type="checkbox"/>	192.168.1.163	Not Selected for Processing.
<input checked="" type="checkbox"/>	ws131	Running

USB CopyNotify! Server IP Address: 192 . 168 . 1 . 1

USB CopyNotify! Clients

- Add Machine Details
- Remove Machine Details
- Select All
- DeSelect All
- Install USB CopyNotify!
- Un Install USB CopyNotify!
- Install Status Check
- Save**
- Exit
- Cancel



USB CopyNotify! (Ver. 2.1)

Control & Monitor USB Device Usage
REMOTE DEPLOYMENT WIZARD

Exit:

This will allow you to exit the application.